

OpcApplicationConfiguration Members

Namespace: Opc.UaFx

Assemblies: Opc.UaFx.Advanced.dll, Opc.UaFx.Advanced.dll

The [OpcApplicationConfiguration](#) type exposes the following members.

Constructors

OpcApplicationConfiguration()

C#

```
public OpcApplicationConfiguration()
```

OpcApplicationConfiguration(OpcApplicationType)

C#

```
public OpcApplicationConfiguration(OpcApplicationType applicationType)
```

Parameters

`applicationType` [OpcApplicationType](#)

Methods

LoadClientConfig(String)

C#

```
public static OpcApplicationConfiguration LoadClientConfig(string configSectionName)
```

Parameters

`configSectionName` [String](#)

Returns

[OpcApplicationConfiguration](#)

Exceptions

[ArgumentNullException](#)

LoadClientConfigFile(String)

C#

```
public static OpcApplicationConfiguration LoadClientConfigFile(string filePath)
```

Parameters

filePath [String](#)

Returns

[OpcApplicationConfiguration](#)

Exceptions

[ArgumentNullException](#)

LoadClientServerConfig(String)

C#

```
public static OpcApplicationConfiguration LoadClientServerConfig(string configSectionName)
```

Parameters

configSectionName [String](#)

Returns

[OpcApplicationConfiguration](#)

Exceptions

[ArgumentNullException](#)

LoadClientServerConfigFile(String)

C#

```
public static OpcApplicationConfiguration LoadClientServerConfigFile(string filePath)
```

Parameters

filePath String

Returns

OpcApplicationConfiguration

Exceptions

ArgumentNullException

LoadDiscoveryServerConfig(String)

C#

```
public static OpcApplicationConfiguration LoadDiscoveryServerConfig(string configSectionName)
```

Parameters

configSectionName String

Returns

OpcApplicationConfiguration

Exceptions

ArgumentNullException

LoadDiscoveryServerConfigFile(String)

C#

```
public static OpcApplicationConfiguration LoadDiscoveryServerConfigFile(string filePath)
```

Parameters

filePath String

Returns

OpcApplicationConfiguration

Exceptions

ArgumentNullException

LoadFromConfig(ApplicationType, String)

C#

```
public static OpcApplicationConfiguration LoadFromConfig(ApplicationType applicationType,  
string configSectionName)
```

Parameters

applicationType ApplicationType

configSectionName String

Returns

OpcApplicationConfiguration

Exceptions

ArgumentNullException

LoadFromConfigFile(ApplicationType, String)

C#

```
public static OpcApplicationConfiguration LoadFromConfigFile(ApplicationType  
applicationType, string filePath)
```

Parameters

applicationType ApplicationType

filePath String

Returns

OpcApplicationConfiguration

Exceptions

ArgumentNullException

LoadServerConfig(String)

C#

```
public static OpcApplicationConfiguration LoadServerConfig(string configSectionName)
```

Parameters

configSectionName String

Returns

OpcApplicationConfiguration

Exceptions

ArgumentNullException

LoadServerConfigFile(String)

C#

```
public static OpcApplicationConfiguration LoadServerConfigFile(string filePath)
```

Parameters

filePath String

Returns

OpcApplicationConfiguration

Exceptions

ArgumentNullException

Validate()

Ensures that the application configuration is valid.

C#

```
public void Validate()
```

Exceptions

OpcException

The configuration is invalid.

Validate(OpcContext)

Ensures that the application configuration is valid.

C#

```
public void Validate(OpcContext context)
```

Parameters

context OpcContext

Exceptions

OpcException

The configuration is invalid.

Table of Contents

Constructors	1
OpcApplicationConfiguration()	1
OpcApplicationConfiguration(OpcApplicationType)	1
Methods	1
LoadClientConfig(String)	1
LoadClientConfigFile(String)	2
LoadClientServerConfig(String)	2
LoadClientServerConfigFile(String)	3
LoadDiscoveryServerConfig(String)	3
LoadDiscoveryServerConfigFile(String)	3
LoadFromConfig(ApplicationType, String)	4
LoadFromConfigFile(ApplicationType, String)	4
LoadServerConfig(String)	5
LoadServerConfigFile(String)	5
Validate()	6
Validate(OpcContext)	6