

OpcTextVariableNode Members

Namespace: Opc.UaFx

Assemblies: Opc.UaFx.Advanced.dll, Opc.UaFx.Advanced.dll

The [OpcTextVariableNode](#) type exposes the following members.

Constructors

OpcTextVariableNode(IopcNode, OpcName)

Initializes a new instance of the [OpcTextVariableNode](#) class accessible by the `name` specified as a child node of the `parent` node given.

C#

```
public OpcTextVariableNode(IopcNode parent, OpcName name)
```

Parameters

`parent` [IopcNode](#)

The [IopcNode](#) used as the parent node or a null reference (Nothing in Visual Basic) in the case there is no parent node available.

`name` [OpcName](#)

The [OpcName](#) through that the new text variable node can be accessed.

OpcTextVariableNode(IopcNode, OpcName, OpcNodeId)

Initializes a new instance of the [OpcTextVariableNode](#) class accessible by the `name` and `id` specified as a child node of the `parent` node given.

C#

```
public OpcTextVariableNode(IopcNode parent, OpcName name, OpcNodeId id)
```

Parameters

`parent` [IopcNode](#)

The [IopcNode](#) used as the parent node or a null reference (Nothing in Visual Basic) in the case there is no parent node available.

`name` [OpcName](#)

The [OpcName](#) through that the new text variable node can be accessed.

`id` [OpcNodeId](#)

The [OpcNodeId](#) through that the new text variable node can be identified and accessed.

OpcTextVariableNode(IOPcNode, OpcName, OpcNodeId, OpcText)

Initializes a new instance of the `OpcTextVariableNode` class accessible by the `name` and `id` specified with the initial value defined by `value` as a child node of the `parent` node given.

C#

```
public OpcTextVariableNode(IOPcNode parent, OpcName name, OpcNodeId id, OpcText value)
```

Parameters

`parent` `IOPcNode`

The `IOPcNode` used as the parent node or a null reference (Nothing in Visual Basic) in the case there is no parent node available.

`name` `OpcName`

The `OpcName` through that the new text variable node can be accessed.

`id` `OpcNodeId`

The `OpcNodeId` through that the new text variable node can be identified and accessed.

`value` `OpcText`

The initial value of the new text variable node.

OpcTextVariableNode(IOPcNode, OpcName, OpcText)

Initializes a new instance of the `OpcTextVariableNode` class accessible by the `name` specified with the initial value defined by `value` as a child node of the `parent` node given.

C#

```
public OpcTextVariableNode(IOPcNode parent, OpcName name, OpcText value)
```

Parameters

`parent` `IOPcNode`

The `IOPcNode` used as the parent node or a null reference (Nothing in Visual Basic) in the case there is no parent node available.

`name` `OpcName`

The `OpcName` through that the new text variable node can be accessed.

`value` `OpcText`

The initial value of the new text variable node.

OpcTextVariableNode(OpcName)

Initializes a new instance of the `OpcTextVariableNode` class accessible by the `name` specified.

C#

```
public OpcTextVariableNode(OpcName name)
```

Parameters

`name` `OpcName`

The `OpcName` through that the new text variable node can be accessed.

OpcTextVariableNode(OpcName, OpcNodeId)

Initializes a new instance of the `OpcTextVariableNode` class accessible by the `name` and `id` specified.

C#

```
public OpcTextVariableNode(OpcName name, OpcNodeId id)
```

Parameters

`name` `OpcName`

The `OpcName` through that the new text variable node can be accessed.

`id` `OpcNodeId`

The `OpcNodeId` through that the new text variable node can be identified and accessed.

OpcTextVariableNode(OpcName, OpcNodeId, OpcText)

Initializes a new instance of the `OpcTextVariableNode` class accessible by the `name` and `id` specified with the initial value given by `value`.

C#

```
public OpcTextVariableNode(OpcName name, OpcNodeId id, OpcText value)
```

Parameters

`name` `OpcName`

The `OpcName` through that the new text variable node can be accessed.

`id` `OpcNodeId`

The `OpcNodeId` through that the new text variable node can be identified and accessed.

`value` `OpcText`

The initial value of the new text variable node.

OpcTextVariableNode(OpcName, OpcText)

Initializes a new instance of the [OpcTextVariableNode](#) class accessible by the `name` specified with the initial value given by `value`.

C#

```
public OpcTextVariableNode(OpcName name, OpcText value)
```

Parameters

`name` [OpcName](#)

The [OpcName](#) through that the new text variable node can be accessed.

`value` [OpcText](#)

The initial value of the new text variable node.

Properties

Value

Gets or sets the value of the text variable node.

C#

```
public OpcText Value { get; set; }
```

Property Value

[OpcText](#)

A [OpcText](#) representing the value of the text variable node. This can be also a null reference (Nothing in Visual Basic).

Methods

ReadTextValue(OpcReadVariableValueContext)

Reads the text variable node value using the `context` specified.

C#

```
public OpcText ReadTextValue(OpcReadVariableValueContext context)
```

Parameters

`context` [OpcReadVariableValueContext](#)

The `OpcReadVariableValueContext` to use to read the text variable node value.

Returns

`OpcText`

The `OpcText` variable node value associated with this node and read using the `context` specified. This can also be a null reference (Nothing in Visual Basic).

Exceptions

`ArgumentNullException`

The `context` is a null reference (Nothing in Visual Basic).

WriteTextValue(`OpcWriteVariableValueContext`, `OpcText`)

Writes the `value` to the text variable node value using the `context` specified.

C#

```
public void WriteTextValue(OpcWriteVariableValueContext context, OpcText value)
```

Parameters

`context` `OpcWriteVariableValueContext`

The `OpcWriteVariableValueContext` to use to write the text variable node `value` specified.

`value` `OpcText`

The `OpcText` to write to the text variable node value.

Exceptions

`ArgumentNullException`

The `context` is a null reference (Nothing in Visual Basic).

Table of Contents

Constructors	1
OpcTextVariableNode(IOPCNode, OpcName)	1
OpcTextVariableNode(IOPCNode, OpcName, OpcNodeld)	1
OpcTextVariableNode(IOPCNode, OpcName, OpcNodeld, OpcText)	2
OpcTextVariableNode(IOPCNode, OpcName, OpcText)	2
OpcTextVariableNode(OpcName)	3
OpcTextVariableNode(OpcName, OpcNodeld)	3
OpcTextVariableNode(OpcName, OpcNodeld, OpcText)	3
OpcTextVariableNode(OpcName, OpcText)	4
Properties	4
Value	4
Methods	4
ReadTextValue(OpcReadVariableValueContext)	4
WriteTextValue(OpcWriteVariableValueContext, OpcText)	5